

Rental

How can I manage the maintenance of a replacement car?

PlanManager can be used to keep track of the maintenance of your courtesy cars. By setting certain parameters the system will also alert you when it's time for a new service.

1. Keeping track of maintenance services.

on the tab "Car Fleet"> "courtesy car" you get a list of all replacement cars in PlanManager. Click in the list on the replacement car where you want fill in a maintenance service. On the left bottom side of the page that opens, you can fill in the service (s) that the car has had.

The screenshot shows the PlanManager interface for a 'Courtesy Car'. The main window displays car details for 'Deans Body Repair' (VAUXHALL ASTRA). The 'New Checkup' window is open, allowing the user to enter the details of a new maintenance service. A green arrow points from the 'New Checkup' button in the table to the pop-up window.

Car Details:

- Location: Deans Body Repair
- Number: 555
- VIN: W0L07PL1234567890
- Registration: DE16BBB
- Make: VAUXHALL
- Model: ASTRA
- Category: A
- Type: Hatchback
- Co2: 120
- Colour: Blue
- Number of doors: 5
- Fuel tank capacity: 55
- Fueltype: Petrol
- Gearbox: Manual
- GPS: ☒
- 4x4: ☐
- Airco: ☒
- Alloy: ☒
- Towir hook: ☐
- Roof: ☐
- Seve seats: ☐

New Checkup Table:

Repaier	Date	Mileage	Cost
REPAIRER 1	09-11-2016	15000	£ 187.00

New Checkup Form:

- Repaier: REPAIRER 1
- Date: 02-08-2017
- Mileage: 29978
- Cost: £ 489
- Comment: all filters replaced, oil change, complete checkup

You will then see a pop-up where you can enter the details of the service. Press save to add the data. The new maintenance appears in the table on the left.

2. Automatic alerts

You can configure PlanManager to automatically display a notification when a new maintenance is necessary. To apply this control you need to set this per vehicle.

2.1 Setting up a vehicle for automatic alerts

Go to the "Car Fleet"> "courtesy car" page and click on ⇨ Show more details. In the

Rental

middle you will see the fields Checkup Interval Months and Checkup Interval KM. Put in the months and km according the car.

The screenshot shows a form for vehicle configuration. On the left, a link says "Show more details." with a green arrow pointing left. The form is divided into three columns. The first column contains fields for Greencard nr, Excess (€ 250), UsualDriver (select a user), Insurance (BA), Greencard duedate, and Coc duedate. The second column contains Mileage (30112), Checkup Interval Months (12), Checkup Interval KM (15000), Winter Tires (in store), Summer Tires (in use), All Season Tires (- Select One -), and Damage. The third column contains Lease Company (Courtesi), Assistance Provider (AA), Driving From (09-11-2016), and Driving Until (31-12-2017). A button at the bottom right says "Change vehicle to INACTIVE". Green arrows point from the "Show more details." link to the "Checkup Interval Months" and "Checkup Interval KM" fields.

2.2 Premature messages

PlanManager will give the messages according to the set time intervals. You can set yourself how long in advance you will get this message. This can be done on the tab "System"> "Options" with the two configurations "CHECKUP_WARNING_MILEAGE" and "CHECKUP_WARNING_WEEKS".

BLOCKNRS_MISSING	tile view
CARPASSTHRESHOLD	general 7
CHECKUP_WARNING_MILEAGE	rental 1000
CHECKUP_WARNING_WEEKS	rental 4
COPY_FROM_FILE	rental number, plate, driver
CREATE_INVOICE_ON_ESTIMATION_SET	invoicing Ja

CHECKUP_WARNING_MILEAGE: enter how many kilometers before reaching the limit you want to display the message. The default setting is 1000km.

CHECKUP_WARNING_WEEKS: enter how many weeks before the period is over you will see the message. The default setting is 4 weeks.

Unique solution ID: #1558

Author: Jean-Marie

Last update: 2021-11-10 16:12